
Site Class Setup

Last Modified on 10/09/2026 1:01 pm PDT

Pathway: *Setup > Account > Site Class*

Site Class Setup categorizes sites within an account and is primarily used in target pricing.




SITE CLASS ID	NAME	TARGET PRICING DEFAULT WEIGHT CLASS	ESTIMATED CUBIC YARD	GEOFENCE RADIUS (METERS)	GL SEGMENT	ACTIVE
1001	RO	Medium	1245	10	RORO	Yes
1002	COM	Light	154	10	FLFL	Yes
1003	MULTI	Heavy	350	20	MULT	No
1004	MUNI	Heavy	200	6	MUNI	Yes
1005	RES	Light	150	4	RESI	Yes

Field Descriptions

Field	Description
Site Class ID	System generated unique identifier.
Name *Required*	The name of the Site Class.
Target Pricing Default Weight Class	Optional setup to categorize sites by and can be used to suggest target pricing when quoting customers. Options include: Light, Medium, and Heavy.
Estimated Cubic Yard	The estimated cubic yards of waste expected to be produced by a site under this site class.
Geofence Radius (Meters) *Required*	Creates a virtual perimeter around the location's address to indicate proximity of the truck to the site. Geofence radius here **overrides** the geofence radius assigned on the account class. **NOTE:** Setting the radius too low (e.g., 1 meter) can interfere with Residential Mode in NavuNav, potentially preventing the app from recognizing when the driver has moved on from one bin to the next. Lowest recommended setting is 20 meters.
GL Segment	The GL Segment for the Site Class, if one applies. GL Segmentation can be defined using Generator Type for Unearned Revenue, Revenue, Surcharge, Tax, and Franchise Fee areas. Check out Setup > Accounting > GL Segmentation for more details and to check the length defined.
Active *Required*	Enables the site class for use. • Yes - Active • No - Inactive

Add/Edit a Site Class

To add/edit a Site Class use the following steps. Once created, it will be selectable in the Site Class field when adding or modifying a site.



To Add


1. Click the **green +** icon to open the *Create Site Class* screen.
2. Complete the following required fields:
    - Enter a descriptive **Name** for the Site Class.
    - Enter the **Geofence Radius** in meters.
    - Select 'Yes' from the **Active** status drop down.
3. Complete additional fields based on your company's established procedures.
4. Click **Save** when finished.

To Edit

Double-click on the row that needs to be modified from the Setup screen. Make the change and then click **Save**.

Application of a Site Class

The Site Class configurations that are set up here are visible and used when creating or editing a site. Site Class is a required field that helps to categorize sites and to define target pricing and specific route requirements.



Related Articles

Add a New Site & Move Between Sites
GL Segmentation Setup