
Database Query - Division Cost Entity

Last Modified on 10/15/2026 10:49 am PDT

Pathway: Database > Database Query


The **Division Cost** entity provides the ability to track, report and export division-level cost and target-rate data, with rows associating a division to a line of business (LOB), material type, service region, and effective date.




Initiating a Division Cost Query

To generate a **Division Cost** report using the Database Query tool, follow the steps outlined below. Reference the Database Query article for more details on how to use the tool for reporting.

1. Go to the *Database > Database Query* screen.
2. Click the **New** button in the top control bar. This will open the **Select Main Entity** popup.
3. Select **Division Cost**.
4. After the **Display Fields** for the **Division Cost** entity populate, select the check boxes for the fields you want to include in the report.
    - If a specific order is required, select the fields in the order you want them to appear in the query.
5. Click **Run** to execute the query. Results are generated in a new tab with the date and timestamp.





Columns Available for Display and Filtering


The following data can be pulled in when running a **Division Cost** report.

Field Name	Description
Division / LOB / Service Region	
Division Id	Identifier for the division associated with the cost and rate settings.
Division Name	Name of the division associated with the cost and rate settings.
Effective Date	Date on which the division's cost and rate settings become effective.

Field Name	Description
Lob Id	Identifier for the line of business associated with the settings.
Lob Name	Name of the line of business associated with the settings.
Service Region Id	Identifier for the service region associated with the settings.
Service Region Name	Name of the service region associated with the settings.
Cost and Markup Information	
Cost Per Mile/km	Cost charged or allocated per mile or kilometer.
Disposal Cost	Disposal cost amount associated with the division's material and service settings.
Disposal Cost Uom	Unit of measure used for the disposal cost, such as ton.
Disposal Cost Uom Id	Identifier for the unit of measure used for the disposal cost.
Labor Cost Per Lift	Labor cost assigned to each lift or service event.
Operating Cost Per Hour	Operating cost assigned per hour.
Markup Factor	Multiplier used to apply a markup to the applicable cost or rate.
Material and Rate Information	
Material Type Id	Identifier for the material type associated with the cost and rate settings.
Material Type Name	Name of the material type associated with the cost and rate settings.
Heavy Pounds Per Cubic Yard	Configured weight in pounds per cubic yard for the heavy material category.
Heavy Target Rate Per Cubic Yard	Target rate per cubic yard for the heavy material category.
Medium Pounds Per Cubic Yard	Configured weight in pounds per cubic yard for the medium material category.
Medium Target Rate Per Cubic Yard	Target rate per cubic yard for the medium material category.
Light Pounds Per Cubic Yard	Configured weight in pounds per cubic yard for the light material category.
Light Target Rate Per Cubic Yard	Target rate per cubic yard for the light material category.

Data Source

The **Division Cost** entity uses the cost and target pricing information configured on the **Division > Cost / Target Pricing** tab of the *Setup > System > Division* screen.



Related Articles

Database Query