

Site Class Setup

Last Modified on 04/15/2026 12:38 pm PDT

Pathway: [Setup](#) > [Account](#) > [Site Class](#)

Site Class Setup categorizes sites within an account and is primarily used in target pricing.


| SITE CLASS ID | NAME | TARGET PRICING DEFAULT WEIGHT CLASS | ESTIMATED CUBIC YARD | GEOFENCE RADIUS (METERS) | GL SEGMENT | ACTIVE |
|---------------|-------|-------------------------------------|----------------------|--------------------------|------------|--------|
| 1001 | RO | Medium | 1245 | 10 | RORO | Yes |
| 1002 | COM | Light | 154 | 10 | FLFL | Yes |
| 1003 | MULTI | Heavy | 350 | 20 | MULT | No |
| 1004 | MUNI | Heavy | 200 | 6 | MUNI | Yes |
| 1005 | RES | Light | 150 | 4 | RESI | Yes |

Field Descriptions

| Field | Description |
|---|---|
| Site Class ID | System generated unique identifier. |
| Name <i>Required</i> | The name of the Site Class. |
| Target Pricing Default Weight Class | Optional setup to categorize sites by and can be used to suggest target pricing when quoting customers. Options include: Light, Medium, and Heavy. |
| Estimated Cubic Yard | The estimated cubic yards of waste expected to be produced by a site under this site class. |
| Geofence Radius (Meters) <i>Required</i> | Creates a virtual perimeter around the location's address to indicate proximity of the truck to the site. Geofence radius here overrides the geofence radius assigned on the account class. NOTE: Setting the radius too low (e.g., 1 meter) can interfere with Residential Mode in NavuNav, potentially preventing the app from recognizing when the driver has moved on from one bin to the next. Lowest recommended setting is 20 meters. |
| GL Segment | The GL Segment for the Site Class, if one applies. GL Segmentation can be defined using Generator Type for Unearned Revenue, Revenue, Surcharge, Tax, and Franchise Fee areas. Check out Setup > Accounting > GL Segmentation for more details and to check the length defined. |
| Active <i>Required</i> | Enables the site class for use. <ul style="list-style-type: none"> • Yes - Active • No - Inactive |

Add/Edit a Site Class

To add/edit a Site Class use the following steps. Once created, it will be selectable in the Site Class field when adding or modifying a site.



To Add

1. Click the **green +** icon to open the *Create Site Class* screen.
2. Complete the following required fields:
 - o Enter a descriptive **Name** for the Site Class.
 - o Enter the **Geofence Radius** in meters.
 - o Select 'Yes' from the **Active** status drop down.
3. Complete additional fields based on your company's established procedures.
4. Click **Save** when finished.

To Edit

Double-click on the row that needs to be modified from the Setup screen. Make the change and then click **Save**.

Application of a Site Class

The Site Class configurations that are set up here are visible and used when creating or editing a site. Site Class is a required field that helps to categorize sites and to define target pricing and specific route requirements.

ADD SITE ? X

Basic Settings | **Billing Settings** | BIC Profile

| | | | |
|---|---|----------------------------|----------------------|
| NAME | <input type="text"/> | DIVISION | Select Division |
| NAME 2 | <input type="text"/> | SERVICE REGION | <input type="text"/> |
| ADDRESS LINE 1 | Enter a location | TAX REGION | <input type="text"/> |
| ADDRESS LINE 2 | <input type="text"/> | ORIGIN | <input type="text"/> |
| CITY/STATE/POSTAL CODE | <input type="text"/> <input type="text"/> | SOURCE | <input type="text"/> |
| PHONE 1 | <input type="text"/> (201) 555-0123 | SALES REP | <input type="text"/> |
| PHONE 2 | <input type="text"/> (201) 555-0123 | STATUS | <input type="text"/> |
| OLD ID | <input type="text"/> | SITE CLASS | <input type="text"/> |
| PO# | <input type="text"/> | GENERATOR | COM |
| SIGNATURE REQUIRED <input type="checkbox"/> | LEED REPORTABLE <input type="checkbox"/> | EPA | MUNI |
| | VIP <input type="checkbox"/> | STATE ID | RES |
| | | ADDITIONAL SERVICE MINUTES | RO |

NOTE:

WARNING ON OPEN:

ACCESS INFORMATION:

BUSINESS HOURS / SERVICE WINDOW:

SAVE

Related Articles

- [Add a New Site & Move Between Sites](#)
- [GL Segmentation Setup](#)